
// prestashop · user guide

Mega Menu Pro

Version 1.0.0
ecom-addons.com

Mega Menu Pro designs the main menu of your shop visually: mega panels with columns you add and resize, vertical tabs, banners, subcategories and products that follow your catalog, sticky or transparent positions and a mobile drawer, in about 6 KB of code and with real links for search engines.



A mega menu: the subcategories of the category, its first product and a promo banner, all from your catalog.


Requirements

Component	Version
PrestaShop	8.1 · 8.2 · 9.0
PHP	8.1 or later
Theme	Any theme that prints the `displayTop` hook (to replace its menu) or `displayNavFullWidth` (a bar under the header): Classic, Hummingbird and the ecom-addons themes do

Installation

1. Download the latest version from **My account › Downloads** on ecom-addons.com.
2. In the back office, go to **Modules › Module Manager** and click **Upload a module**; choose the zip file.
3. Open **Configure** on **Mega Menu Pro**. Nothing changes in your shop until you use a menu.

Create a menu in one click



Start from a ready-to-go menu built from your own categories, and choose where it appears.

Pick one of the five presets. Each one is built from the top categories of **your** shop (names and links come from the catalog, in every language) and is fully editable:

Preset	Design	What it shows
Mega menu of categories	Mega menu	Wide panels: subcategories in columns, the first product of the category and a promo banner.
Vertical tabs	Vertical tabs	One "Shop" item: hover a category on the left and its content opens on the right.
Full screen cards	Cards	Panels that fill the screen, each group of links on a card, with image banners and a sticky bar.
Classic dropdown	Dropdown	Simple dropdowns with the subcategories and a flyout for the third level.
Minimal, transparent over the hero	Minimal	Positioned over your slider, solid once the page scrolls, with full width panels.


Where the menu appears

Use the three buttons on top of the list:

Choice	What it does
Replace the theme menu	The menu takes the place of the theme's menu in the header (`displayTop`). The theme's own menu (the bundled *Main menu* module, `ps_mainmenu`) is unhooked from that position and given back when you choose another option or uninstall the module.
Below the header	A full width bar under the header (`displayNavFullWidth`); the theme's menu stays.
Off	The theme's menu is used as it is.

Then press **Use this menu** on the card of the menu you want live. Only one menu is live at a time; you can keep as many as you like.

The editor



The editor: the structure on the left, the live menu in the middle where you resize columns and drag blocks, and the settings of the selection on the right.

The preview is the shop's own markup, so it is exactly what visitors get.

Area	What you can do
Top bar	Rename the menu; preview on **desktop, tablet or phone**; **undo / redo**; switch the language of the texts (**EN / ES / FR**); open **Menu settings**; **Save** (it shows when there are unsaved changes, and the page warns you if you leave with them).
Structure (left)	The items of the menu, and under the selected item the columns and blocks of its panel (or its tabs). Drag to reorder; duplicate or delete with the buttons.
Menu (center)	Click an item, a column or a block to select it. Each column has a small bar to move it, add a block or delete it, and a **handle on its right edge**: drag it to change the width (the panel has 12 units). Drag a block to another column. **Add a column** adds one to the open panel.
Settings (right)	The settings of what is selected, in sections.

Keyboard: **Delete** removes the selection, **Ctrl/Cmd + D** duplicates it, **Ctrl/Cmd + Z** and **Shift + Ctrl/Cmd + Z** undo and redo, **Ctrl/Cmd + S** saves.


Items and panels

An item has a **label** (per language, or the name of a category), a **link** (a URL, or pick a category with the search box), an optional **badge** such as *New*, and can be **highlighted** with the accent color. **Add a panel** to open columns under it. A panel has a layout:

- **Columns**: up to six columns of blocks.
- **Vertical tabs**: a list of tabs on the left; each tab has its own columns, shown on the right when you hover or focus the tab.

A panel can have its own **background** (a color and an image placed right, left, at the bottom or covering) and its own **width** (see below). **Fill from a category** builds editable columns with the subcategories of a category; to have columns that follow the catalog by themselves, add a *Subcategories* block instead.

Blocks




Actions that follow your catalog: here, the subcategories of a category, two levels deep, in two columns.

Block	What it does
Links	A title and a list of links (a URL or a category each, with an optional badge). A link can have a **submenu** that opens as a flyout on hover.
Subcategories *(action)*	The subcategories of any category, one or two levels deep, up to 30, in one to four columns, with their images if you want. When the catalog changes, the menu does.
Product *(action)*	A product card with image, name, price and a button: **the first product of a category**, a chosen product, the newest or the best seller.
Image	A banner with a caption and a button text, a link, a proportion (1:1, 4:3, 16:9, 3:4) and an optional dark gradient behind the caption.
Text	A short text per language.
Pages	A list of CMS pages.

Categories, products and pages are chosen with search boxes, never by typing ids.

Menu settings



Menu settings: base design, position, how panels open, items, colors and the mobile version.

Section	Settings
Base design	**Mega menu**, **Dropdown**, **Vertical tabs**, **Cards** or **Minimal**: the look of the bar and panels.
Position	**Normal**; **Sticky** (it sticks to the top once it would scroll away); **Fixed** (always at the top; its room stays reserved so the page does not jump); **Over the page** (on top of your slider or hero), optionally **transparent until the page scrolls**, with its own text color while transparent. Distance from the top, and alignment of the items.
Panels	How they open: **Auto** (as wide as their content, under the item), **Contained** (centered, with a maximum width you choose), **Full width** (edge to edge) or **Full screen** (edge to edge and as tall as the rest of the screen). Open with **hover** (with a delay, so passing over does not open them) or **click**. Animation (fade, slide, scale, none) and speed.
Items	Hover effect (line, pill, fill, none), font size and weight, padding, corner radius, an arrow on items with a panel, uppercase, shadow.
Colors	Bar background and text, hover, accent, panel background and text, borders, badges.
Mobile	The width below which the mobile version shows, and how it opens: **left drawer**, **right drawer** or **full screen**; with or without the word *Menu* next to the burger.

Mobile

Below the breakpoint the bar becomes a burger button. It opens a drawer (or a full screen menu) with the items in a list; the arrow on an item opens its panel as an accordion, one section at a time. **Escape** or the close button closes it and the focus goes back to the burger; the page does not scroll behind it. On a tablet or any touch screen wider than the breakpoint, panels open with a tap on the arrow, since there is no hover.

In the Theme Editor Studio and in Aura

Mega Menu Pro is included in the Aura theme. If you use the Theme Editor, its **Studio** shows a Main menu panel in the Header area, with a live preview: layout (how panels open, content width), position (normal, sticky, fixed or over the page, distance from the top, transparent until the page scrolls, alignment of the items), colors, font size and spacing, behavior (hover effect, open with, animation, arrows, shadow) and the mobile menu. Menu colors are chosen to fit the theme's palette.

The menu also takes part in the **export and import of the look of the shop**: items, panels, banners and images travel in the pack, with links to categories, products and pages found again by what they point to.

Performance and SEO

- A real `<nav>` with a real `<ul>` of `<a href>` links. **Panels are in the page's HTML**, not injected by a script, so search engines and assistive technology read every link. Panels are hidden with CSS (not `display:none` inline), and there are **no headings inside the navigation**.
- Opening a panel on **hover or keyboard focus needs no JavaScript**. The script only adds click mode, the mobile drawer, the fixed and sticky positions and keyboard arrows between items.
- About 4 KB of CSS and 2 KB of JavaScript (gzipped), no dependencies, loaded only when a menu is live. Images are lazy and have a fixed proportion, so nothing moves while they load. On phones the burger shows before the script runs, so there is no jump.
- Accessible: buttons with `aria-expanded` and `aria-controls`, visible focus, **Left / Right** arrows between items, **Escape** to close, and reduced motion respected.
- No third-party requests; your banners are served from your shop (`img/ecommm/`).

Security

Uploads are checked by their content, not their name (JPG, PNG, WebP, AVIF or GIF up to 8 MB) and renamed. Everything the editor sends is cleaned before it is stored: texts are plain text, links must be `http(s)`, a path from the root or an anchor, and file names cannot contain a path.

Uninstalling

Uninstalling (or choosing **Off**) gives the theme's menu back: the bundled *Main menu* module is hooked again. Your menus are deleted with the module; your uploaded images stay in `img/ecommm/`.

Troubleshooting

Problem	What to check
Nothing changed in the shop	On the list, choose **Replace the theme menu** or **Below the header**, and press **Use this menu** on one menu.
I see two menus	You chose **Below the header**: pick **Replace the theme menu** to remove the theme's.
It does not replace my theme's menu	Your theme may not print `displayTop` where its menu is; use **Below the header**, or place the module in **Design › Positions**.
The panel is cut off or too narrow	Choose **Contained**, **Full width** or **Full screen** in *Panels open as*, and check the content width.
The fixed or sticky bar covers the page	Raise *Distance from the top* if your theme has a bar of its own above.
A category is missing from automatic blocks	Only active categories are listed.